# শূদ্দ PETROSYS

# SOFTWARE RELEASE NOTES

## Version 2019.1.1



Petrosys valued-added agile development continues with the release of Petrosys PRO 2019.1 – a major update to Petrosys PRO – which offers new features for users.

Petrosys PRO 2019 solidifies the software's position in the production world by focusing on well data improvements. Often considered as more of an explorationist's tool kit, Petrosys PRO is widely used in production teams globally. After discussing their needs with regards to well data, we have concentrated our development on exchanging well log data and have made some major improvements to the display of well data.

The addition of Well Log Curves to our continuously expanding 'Exchange' capability will be a popular addition for many PRO users. PRO has long been able to exchange well header, tops, directional surveys and checkshot surveys between a variety of 3<sup>rd</sup> party sources and the addition of 'Well Logs' to this option makes PRO an even more proficient data management tool.

Improvements in the direct access to other data from connected G&G applications continue to be a feature of Petrosys PRO releases. PRO 2019.1 gives Petrel users improvements in the selection of seismic and horizon data and drag and drop of Petrel contours; DecisionSpace and Petrel users get a more straightforward ribbon map when they drag and drop a seismic line layer onto Mapping.

To improve the quality of Production Mapping in PRO, our users have asked us to focus on how deviated well paths are displayed. With advancements in geosteering, modern wells may penetrate the top or base of a key reservoir zone repeatedly. In PRO 2019.1 the user can display the multiple intersections as well as display multiple zones in the same display layer. This ability, combined with PRO's direct connections to key data sources, will give production teams easily updateable maps showing the spatial distribution of key producing zones.

Anyone using the PostGIS opensource database will be glad to see the ability to display data directly from the database, exchange data from the database to other sources and the ability to use data from the database as input to grid creation.

Maps drawn outside of the Anglosphere will benefit from improvements in the support for international character sets, ranging from the elusive German ß to the intricacies of Chinese and Japanese text.

Growing user sophistication in the use of Petrosys PRO Surface Modeling has led to several improvements not immediately obvious to the casual user. Lowest closing contour calculations can have sealing faults that don't have to be closed. Prospect outlines based on lowest closing contours may contain 'holes' based on local surface depressions or other structures: Shapefiles with this topology can now be successfully used in Petrosys PRO volumetrics. Point data from Excel and GIS sources can now be optionally regarded as representing lines to allow inclusion of the implied gradient in surface computations. The inclusion of all input data for gridding, and not just that within the current AOI, can now be enabled, as can elliptical search radii.

Read on for more details on these options and more, or for more information please contact your nearest support office or email <u>support@petrosys.com.au</u>.

#### Highlight features introduced in 2019.1

#### **Exchange of Well Log Curves**

The Wells Exchange has added support for exchanging 'Log Curve' data between supported data sources. Users will now be able to read Log Curve data from thirdparty data sources like OpenWorks, Petrel, Paradigm, IHS Kingdom, DUG Insight, ODM and DLIS or LAS files and then be able to write that Log Curve data to OpenWorks and Petrel. In addition to third-party data sources, the Petrosys dbMap PPDM38 data model is supported, where DLIS or LAS files previously catalogued through the Records Management (RM) system can be read during an exchange.

nput Data Source					
Select the data source	you want to import wells from		💮 Well Import V	Vizard	
OpenWorks	•	Connect			
Output Data Source			Select the log cur	ves you want to import	
elect the data source you want to export to			Name	Description	Output Name
			BS BS	Bit Size (Created in Geolog)	BS
Petrel	•	Connect	S BS CALI D DENS D DEPTH D DRHO D DTC D DTS GR GR V NEUT	HRCC Cal. Caliper (HCAL)	CALI
			DENS	HRDD High Resolution Formation Density (RHO8)	DENS
ata Types			DEPTH		DEPTH
	Select the data types	to import	DRHO	HRDD Density Correction (HDRA)	DRHO
	Select the data types	to inport	DTC	Delta-T (DT)	DTC
			DTS	Delta-T Shear - Lower Dipole (DT1)	DTS
	Data Type		GR GR	Gamma-Ray (ECGR)	GR
	Well headers			Enhanced Thermal Neutron Porosity (NPOR)	NEUT
	Formations		PEF	HRDD Standard Resolution Formation Photoelectric Factor	(PEFZ) PEF RESD
	Directional surv	eys	RESD RESM	Array Induction Two Foot Resistivity A90 (AHT90) Array Induction Two Foot Resistivity A30 (AHT30)	RESD
	Log curves		RESM	Array Induction Two Foot Resistivity A30 (AHT30) Array Induction Two Foot Resistivity A10 (AHT10)	RESM
			TEMP	HTC Temperature (HTEM)	TEMP
			RESD RESM RESS TEMP TENS	Cable Tension (TENS)	TENS
				15 active, 0 inactive	
			Name	PEF	Valid name +
< Back Next > 0)		OK	Dictionary id	test_ri	+
			Dictionary desc.		+
			Description	HRDD Standard Resolution Formation Photoelectric Factor (PEFZ)	+



#### **Production Mapping**

Display/Wells introduces the ability to display multiple path segments in the same display layer. The 'Path' panel has been split into the well full path and path segments display. Users can select multiple path segments, with rich control over the segment start and end point. As in previous versions, when selecting formations for multi-connect data sources, it is also possible to specify rules to use formations and/or sources/interpreters in preference to others. Users can select different line styles and colors for each displayed path segment, while certain data sources offer extra color options; for example, Petrel data source will offer Petrel well, Petrel well folder, Petrel formation options.

The value in being able to segment the display styles of well paths is to more effectively map, visually identify and highlight the spatial distribution of key producing zone, sand or reservoir properties; and to more effectively map unconventional and directional drilling programs.

#### **PostGIS Spatial Data Support Added**

PostGIS, the spatial database extender for the PostgreSQL object-relational database, is becoming more popular at some sites, particularly in Norway. We have now added the ability to read PostGIS spatial data. This means users can now find a PostGIS connection available Display/GIS in Mapping, and as an input data source in the Spatial Data Translator and as an input data source when creating a grid.

#### Paradigm 18p1 Support Pack and Petrel 2019.1 Supported

Support for the latest Paradigm 18p1 Support Pack and Petrel 2019.1 has been added for Windows and Linux (Paradigm only). All versions of Paradigm and Petrel supported by Petrosys PRO 2018 remain supported.

#### Improved Support for non-ASCII Text

PRO 2019.1 adds better support for non-ASCII text being used throughout the application. For example, using Arabic characters in a legend or displaying emoji-text as a callout to a map feature. Furthermore, maps containing non-ASCII text can now be shared with other PRO users on any platform with any language preference, confident in the knowledge that the text will display as intended.

#### **Surface Modeling Enhancements**

Several improvements to Surface Modeling have landed in PRO 2019.1. Support for unclosed sealing faults in lowest closing contour calculations and support for polygons with holes in volumetrics makes volumetric workflows simpler. Allowing GIP, Excel and text point data to be interpreted as



line data reduces the data manipulations that previously had to be done to support these workflows. Addition of a pause task type enables user intervention within a workflow while maintaining the benefits of the workflow's context and consistency.

Two features are available as a technology preview to allow interested users to evaluate their usefulness:

- Allowing data outside the grid area to calculate the grid surface
- Enable a search ellipse to restrict the data used to calculate a grid node during surface calculation

Each technology preview feature is disabled by default but can be enabled via the Configuration Tool. Please contact Petrosys Support for assistance in enabling these features or for further details.

#### **Dispatch Server Connections Removed**

Support for Dispatch Server connections, initially deprecated in Petrosys PRO 2018.2, has been removed. All Dispatch Server connections can be replaced with equivalent remote connections if required.

#### **Notes for Upgraders**

Upgraders from Petrosys PRO 2018 should be aware of the following changes:

- The Petrosys Dispatch Server, which allowed access to third-party data sources on remote hosts has been removed. Similar functionality is available through the remote connections feature, which was released in Petrosys PRO 2018.2. Please consult the help documentation or contact Petrosys Support for more information on this feature.
- Petrosys PRO 2019 requires a new license file. Please obtain your license file by logging on to the <u>Petrosys Client</u> <u>Portal</u> or contacting <u>Petrosys Support</u>.
- Petrosys PRO 2019 now saves map files and panels.pnd in the UTF-8 codec. This means earlier versions of Petrosys PRO may not open these files correctly, or the text within them may not display correctly.
- Petrosys PRO 2019 is backwards compatible with Petrosys PRO 2018, except for:
  - Dispatch server connections will not be connected. Petrosys PRO will prompt for a replacement connection.

Upgraders from versions of Petrosys PRO earlier than 2018 should consult the Petrosys PRO 2018 and earlier release notes for any relevant upgrade information.

No environment, third-party data source or operating system updates are required for Petrosys PRO 2019. For a full list of supported environments, please see the <u>Petrosys PRO Supported Environments</u> page.

#### 16 entries

## Detailed Release Notes Summary PRO 2019.1.1

Enhancements

Application - General

74585 Chart Analysis - Added gradient histogram equalisation options

Application - User Interface

74272 Better support for Unicode characters in the application

dbMap - Various panels now better support resizing by expanding the list element

Connections, Import and Export

68670 Improve performance of display of images from tiled map services

Connections, Import and Export - Esri

74421 Added support for SDE data stored in Oracle 18c databases

Mapping - General

- 72229 Support added for merging a dbm that has a different color palette
- 74547 Runtime Text Substitution User name and Application Version fields added
- 74265 Files referenced in CGM files can now resolve relative paths against PSPATH
- 74333 Graphics Support added for FlatCap line end style

Mapping - Map Sheets

74230 Default scanning options for map template and extents can be set via a configuration setting

Surface Modeling - Contouring

73784 Selecting well contact points from formation/zone top/base now supported

Surface Modeling - General

- 66140 Introduce grid vertical sense in 'Compute Dip and Azimuth Grids'
- 74372 Introduce grid vertical units in 'Compute Dip and Azimuth Grids'
- 43295 Added run time scan geometry for grid when importing XYZ file to grid
- 42681 Updated help for Surface Modeling/Grid/Dump faults to document interpolation parameter usage
- 74666 Updated Back Interpolate to WDF help topic

#### 27 entries

## Detailed Release Notes Summary PRO 2019.1.1

**Bug Fixes** 

Application - General

73953 Directories with unencodable characters now handled

#### Connections, Import and Export

- 74225 dbMap PPDM38 Cataloging of DLIS files with empty curves has been fixed
- 74148 Fixed XML/HTML log for well log curves in Well import wizard
- 74140 Improved support for ArcGIS web feature services
- 74221 Missing values are handled correctly by Wells Exchange when wells are imported into OpenWorks

#### Connections, Import and Export - OpenWorks

- 50461 Correct operator and completion date values are now read for OpenWorks well headers
- 74527 Fixed OpenWorks plugin not connecting on some Windows machines

#### Connections, Import and Export - Petrel

74496 Fixed crash when importing 3D seismic coordinates from Petrel to SDF

dbMap - Client

74041 Well Test Dialog no longer crashes when Oracle cursor sharing is enabled

#### Mapping - General

- 73636 Bubble map layer names correctly remember custom layer descriptions
- Title block text for system title blocks is restored correctly when dbm's are reloaded
- 74716 Landgrid /File/Preferences/Tracking panel has more space to display global landgrid file name
- 74223 Color Bar no longer shows negative zero (-0) as axis annotation
- <u>74350</u> Legend font is drawn correctly if set to Default
- 74690 Graphics Custom linestyles with larger scale factor now supported

#### Mapping - Grids, Surfaces and Sampled Data Files

- 74489 Contours computed on the fly from grids can now be exported to spatial data successfully
- 74455 Orthocontouring Crash in panel when creating new group fixed
- 74280 Gridding succeeds after output grid gradient has been edited in mapping

#### Mapping - Publication

74303 Export of raster images with "Map contents only" consistently writes correct georeferencing information

#### Mapping - Wells

- 74588 Formation tops Well name annotation now works with custom format
- 74205 Petrel wells are displayed when data selection changes and dynamic map extent is used
- 74269 Selected zones now highlighted in zone selector picker

Surface Modeling - Contouring

73232 Contouring around faults does not end up in an infinite loop

#### Surface Modeling - General

- 74283 Collecting output files step is much faster for large workflows
- 74339File/Import/Petrosys Grid off by one cell in vertical direction error has been corrected

#### Surface Modeling - Gridding

74277 Point data gridding error when reading Excel using .xft file has been fixed

#### Surface Modeling - Workflows/Scripting

74332 File/OpenWorkflow handles network path correctly

## Petrosys Release Notes

### Petrosys Release PRO 2019.1.1

**Detailed Release Notes** 

#### Application - General

#### Chart Analysis - Added gradient histogram equalisation options

Gradient histogram equalization is now available on the Chart Analysis dialog.

## **Application - General**

#### Directories with unencodable characters now handled 73953

An advanced option has been added to the Grid AOI and Text CRS crawlers so they can handle directory and file names which are not legal within the current system codec. This may occur when files have been created on a shared file system by a system with a different, incompatible codec.

When enabled, file names may be displayed in the user interface and log files incorrectly, but the file contents will be crawled as expected.

#### Application - User Interface

#### Better support for Unicode characters in the application 74272

Building on the work done in PRO 2019.1 this release has improved again the support Unicode characters throughout the application.

Specifically:

- dbm, tsk and 3dm filenames can have Unicode in the filename.
- > Title Block substitution text supports Unicode in the content.
- Excel display via both /Display/GIS and /Display/Excel Table supports Unicode in the Excel filename and Excel content.
- MIssing file resolution supports filenames with Unicode.

#### dbMap - Various panels now better support resizing by expanding the list element 70759

Various panels in the dbMap well header dialogs now better support resizing by expanding the list element.

#### Connections, Import and Export Enhancements

#### Improve performance of display of images from tiled map services 68670

The time taken to download and display images from tiled raster services (for example, Bing Maps, WMTS, ArcGIS) has been significantly improved, with an approximate speed up of 25x for large numbers of tiles.

74585

## **Bug Fixes**

Enhancements

Enhancements



#### **Bug Fixes**

#### dbMap PPDM38 - Cataloging of DLIS files with empty curves has been fixed

74225

In previous version when cataloging DLIS files to PPDM38 dbMap, if the DLIS had empty curves the cataloging process will fail. Now it will succeed by ignoring the empty curves.

#### Fixed XML/HTML log for well log curves in Well import wizard 74148

In previous version well import wizard does not generate correct HTML report for well log curves exchange. This has now been fixed.

#### Improved support for ArcGIS web feature services 74140

Improvements have been made to the methodology for accessing ArcGIS web feature services which allows access to some servers (configured with explicit object ids) that did not previously work.

# Missing values are handled correctly by Wells Exchange when wells are imported into OpenWorks 74221

In previous version during well log curves exchange to OpenWorks missing values could be mistakenly treated as non-missing values. This has now been fixed.

#### Connections, Import and Export - Esri Enhancements

#### Added support for SDE data stored in Oracle 18c databases 74421

Petrosys includes support for accessing Esri ArcSDE databases running on an Oracle 18c database. This uses a new method to access the SDE data and needs to be explicitly enabled - please contact Petrosys support for details.

#### Connections, Import and Export - OpenWorksBug Fixes

# Correct operator and completion date values are now read for OpenWorks well headers

The OpenWorks well header WL\_CURRENT\_OPERATOR and COMPLETION\_DATE fields are now being used for the Current Operator and Completion date. Previously the DATA\_RELEASE\_DATE was incorrectly being treated as the Completion date and DRILLING\_OPERATOR as Current operator.

#### Fixed OpenWorks plugin not connecting on some Windows machines

74527

For some Windows machines with OpenWorks installed, it was not able start the OpenWorks DevKit plugin, when trying to display or read 3D seismic surfaces, for example. This has been fixed.

Connections, Import and Export - Petrel

#### Fixed crash when importing 3D seismic coordinates from Petrel to SDF

74496

**Bug Fixes** 

No longer crashes when importing 3D seismic coordinates from Petrel to SDF.

#### dbMap - Client

#### **Bug Fixes**

#### Well Test Dialog no longer crashes when Oracle cursor sharing is enabled

74041

A crash in the Well Test dialog that can occur when Oracle cursor sharing is enabled has been fixed.

#### Mapping - General Enhancements

#### Support added for merging a dbm that has a different color palette 72229

Base Map Template and File/Merge option now support merging .dbm file with different color palette.

# Runtime Text Substitution - User name and Application Version fields added 74547

The runtime text substitution fields <<USER>> and <<PVSNO>> have been added to the help documentation as well as showing up in the green plus (+) button dialog of available fields.

# Files referenced in CGM files can now resolve relative paths against PSPATH 74265

Files that are used in CGM files can now use a relative path, with that relative path then appended to each entry in the standard search path PSPATH when attempting to resolve the file.

For example, if a title block references a PNG file as 'logos/company.png', then Petrosys PRO can resolve this path to the file \$ps\_local/logos/company.png.

#### Graphics - Support added for FlatCap line end style74333

Support has been added for the "FlatCap" line end style for graphical lines. This line style end stops right on the start/end of the line, in contrast to the "Butt' style which extends half a line width beyond the start/end point.

This style is accessible in the standard line style selector dialog.

Mapping - General

#### Bug Fixes

#### Bubble map layer names correctly remember custom layer descriptions

73636

Changes to bubble maps in Petrosys PRO version 2018.3 introduced a bug where custom layer names for bubble map layers would be reverted to the default whenever the layer was edited. This now works as expected.

# Title block text for system title blocks is restored correctly when dbm's are reloaded 74252

In previous versions, user entered text for "System" title blocks would sometimes not be displayed correctly when reopening dbm files. This would occur when opening a dbm in a different version of Petrosys and where the current displayed title block was the same as the dbm.

# Landgrid - /File/Preferences/Tracking panel has more space to display global landgrid file name 74716

In the /File/Preferences/Tracking panel, there is now more space to display the global landgrid file name so that it does not display truncated it if is more than 28 characters long.

#### Color Bar no longer shows negative zero (-0) as axis annotation

74223

In previous versions, the Display/Color Bar option could display negative axis values that were very close to zero as negative zero (-0).

#### Legend font is drawn correctly if set to Default 74350

The font used for drawing the legend will now be used correctly if it is set to "Default". It will inherit the application default font as set in /File/Preferences/Mapping.

#### Graphics - Custom linestyles with larger scale factor now supported 74690

Custom linestyles with larger scale factor now supported. Previously scale factors above about 4 could cause the application to crash.

### Mapping - Grids, Surfaces and Sampled Data FilesBug Fixes

# Contours computed on the fly from grids can now be exported to spatial data successfully 74489

In previous versions there was a bug that in grid colorfill display contours generated on the fly couldn't be exported to shapefile, Excel, etc. if the current map sheet CRS differs from the grid CRS. This has now been fixed.

#### Orthocontouring - Crash in panel when creating new group fixed 74455

The /Display/Grid/Orthocontours option could error and crash when accessing newly created Culture groups. This bug was introduced in 2019.1 and has now been fixed.

#### Gridding succeeds after output grid gradient has been edited in mapping

74280

**Bug Fixes** 

Surface modeling gridding process succeeds after the output grid has been used for gradient editing in mapping.

#### Mapping - Map Sheets Enhancements

# Default scanning options for map template and extents can be set via a configuration setting 74230

When selection map templates and extents, there are options to enable or disable scanning of legacy map sheet files and dbm files (for extents). A configuration option has been added to control the default behaviour (i.e. the settings for the first time Petrosys is run in a particular project)

#### Mapping - Publication

# Export of raster images with "Map contents only" consistently writes correct georeferencing information 74303

Previous versions of Petrosys PRO would occasionally write incorrect georeferencing information when exporting raster images from the File/Export/Raster option with "Map contents only" enabled.

#### Mapping - Wells

## Formation tops - Well name annotation now works with custom format

When displaying wells in Mapping, the Custom format option on the Formation tops tab now annotates the Well name at the formation location when selected. Previously the well name did not appear on the map.

It is also now possible to annotate other well header attributes at the formation location by typing them into the Custom format field. e.g. the well UWI can be added by typing in <<UWI>>.

# Petrel wells are displayed when data selection changes and dynamic map extent is used 74205

Petrel wells display works correctly when the filtering (Data selection) is changed and dynamic map extent is being used.

### Selected zones now highlighted in zone selector picker 74269

Zones selected as path segments in Display/Wells are highlighted in the zone selector picker.

## Surface Modeling - Contouring Enhancements

## Selecting well contact points from formation/zone top/base now supported

73784

**Bug Fixes** 

**Bug Fixes** 

In Surface Modeling it is now supported to select well contact points directly from well formation/zone top/base.

## Surface Modeling - Contouring

### Contouring around faults does not end up in an infinite loop 73232

In previous version Mapping or Surface Modeling could hang or crash due to contouring entering an infinite loop. This has now been fixed.

Surface Modeling - General Enhancements

#### Introduce grid vertical sense in 'Compute Dip and Azimuth Grids' 66140

Vertical sense has been added to Compute Dip and Azimuth in order to calculate correct gradients for various grid depth scenarios.

## Introduce grid vertical units in 'Compute Dip and Azimuth Grids' 74372

Vertical units has been added to compute dips correctly where the grid z value units might differ from XY units.

## Added run time scan geometry for grid when importing XYZ file to grid

Ability to scan imported data for area of interest at task run time has been added for File/Import/XYZ Ascii to grid file option.

# Updated help for Surface Modeling/Grid/Dump faults to document interpolation parameter usage 42681

Grid/Dump faults help page has been updated.

#### Updated Back Interpolate to WDF help topic

Updated help topic for Grid/Back Interpolate/WDF.

### Collecting output files step is much faster for large workflows 74283

Collecting output files has been optimized and runs significantly faster.

#### File/Import/Petrosys Grid off by one cell in vertical direction error has 74339 been corrected

File/Import/Petrosys grid calculates correct origin. This may be half cell off from imported data.

## Surface Modeling - Gridding

#### Point data gridding error when reading Excel using .xft file has been fixed 74277

In previous version the file read time in column file format string saved in .tsk is incorrect which could cause some errors when reading data from Excel. This has now been fixed.

Surface Modeling - Workflows/Scripting

### File/OpenWorkflow handles network path correctly74332

File/OpenWorkflow handles network paths correctly.

Surface Modeling - General

# **Bug Fixes**

**Bug Fixes** 

**Bug Fixes** 

## Detailed Release Notes Summary PRO 2019.1

Enhancements

#### 3D Viewer - General

62761 OpenInventor upgraded to 9.7.2

#### Application - General

73383 During file resolution check any relative files against current project directory

73416 Check path mappings against all applicable path mapping

Application - User Interface

71389 Infinite number of decimal places for decimal value entry

#### Configuration - General

- 73348 Allow From path mapping to be a blank path
- T3882 LIMS Spotfire links updated (Santos)

#### Configuration - Licensing

- 73764 Tools/License Manager (Windows) Leading and trailing spaces are stripped from hostname when using "Edit/License Server Connection Configuration"
- 73012 Petrosys PRO 2019.1 requires a new license file

#### Connections, Import and Export

- 71518 Removed Dispatch Server and support for Dispatch Server typed connections in the Connection Manager
- <u>36485</u> Support added for reading PostGIS spatial data
- 72606 Flash wells option added to Well list for DevKit data sources
- 72525 Drag and drop of 2D seismic horizons now creates a layer with just ribbon map displayed
- 72520 Petrel Drag-and Drop into grid input data only prompts when required
- 72278 Petrel DnD Dragging 2D Seismic horizons now filters lines by the Petrel survey folder

#### Connections, Import and Export - Paradigm-Epos

73705 Added support for Paradigm 18p1 Support Pack on Linux and Windows

#### Connections, Import and Export - Petrel

#### 70813 Petrel 2019.1 supported

- 72635 Petrel 2D seismic Filtering by Seismic folder is now available in Mapping and Surface Modeling
- 72270 Petrel DnD Default item/layer names are now more descriptive for 2D and 3D horizons

#### Mapping - Editors

73977 Well Symbol Generator - Added in 72 and 60 degree arc primitives

#### Mapping - General

- <u>31024</u> /Display/Text has improved support for international character sets
- 63253 Improved layer selection in the Display/Web Service Image/WMS layer selector
- 52961 The selected layer in the Mapping display list is more obviously highlighted
- 63443 Display of contours from Petrel added

#### Mapping - GIS, Spatial and Culture

20227 Display/GIS thematic mapping allows polygon outline lines to be turned off

#### Mapping - Grids, Surfaces and Sampled Data Files

#### 73436 Contour on-the-fly performance improved

#### Mapping - Wells

- <u>30474</u> Display/Wells Path Segments Allow multiple segments in a single display layer
- Add support for reading zones from Petrel
- 53013 Display/Wells/Path Segments fixed logic when well intersects formation multiple times

#### Surface Modeling - Exchange

43990 Wells Exchanges now supports Log Curve data

46621 Exchange/Wells Import Wizard menu has been renamed to Exchange/Wells

#### Surface Modeling - General

- 15476 Mean and median grid filter added
- 72080 Lowest closing contour now supports sealing faults that are not closed

#### Surface Modeling - Gridding

- 73544 Grid outlining performance improved
- 73488 Boundary gridding displays error message when not valid data
- 72382 Grid/Create grid allows users to select input point data type (point or line) for GIP, text and Excel data

Surface Modeling - Volumetrics

#### 72397 Use polygons with holes in volumetrics

- Surface Modeling Workflows/Scripting
- 30618 Pause functionality added to Surface Modeling workflows
- 68862 Tools/DrawMap scripting now insensitive to template dbm layer order

#### 30 entries

## Detailed Release Notes Summary PRO 2019.1

**Bug Fixes** 

#### 3D Viewer - General

69912 Visual Studio 2015 OpenMP library now installed

Application - General

73860 Centreline faults are supported in the Esri ArcMap plugin

Application - User Interface

54249 Fixed warning message for Oracle password due to expire

73075 List filter dialogs now follow parent dialog moves

#### Connections, Import and Export

- 74029 Performance improved when filtering by Paradigm-Epos well DB
- 73889 Exchange 3D Seismic Surfaces no longer crashes if it cannot connect to the OpenWorks DevKit
- 73002 Exchange 3D seismic surface more tolerant of geometry differences

Connections, Import and Export - Excel

73914 Excel integer values with more than 10 digits are correctly saved

Connections, Import and Export - Petrel

72669 Petrel 2D seismic - Import to SDF and dbMap filtering by Seismic folder now works

#### dbMap - Client

72973 PPDM3.8 Well Checkshot Survey ID, Survey type and Source are now editable

#### Documentation - Online Help

73198 Print dialog launches correct help topic

#### Mapping - Editors

74088Spatial Editor reports correct polygon area when projected CRS for data does not have units of metres69379Grid Editor requires confirmation when editing contours with ungridded changes

#### Mapping - General

- 72558 Map Templates Handle Unicode chars correctly when serialised to dbm
- 74051 Drawing Tools/Closed Shape and Curve Button double click is more reliable on linux
- 73557 Display/Location Map does not crash when enabled for a map with a LocalXY CRS

#### Mapping - GIS, Spatial and Culture

- 71420Display/GIS correctly draws long lines that are close to the central meridian +180 degrees74002Display/GIS shows the correct number of decimal places for maps created prior to 2018.3
- 72389 Display/GIS/Thematic Mapping Series Range allows entries of bound between -1.0 and 0.0

#### Mapping - Grids, Surfaces and Sampled Data Files

64318 Display/Grid contour label size fields are updated correctly when the map scale changes

#### Mapping - Map Sheets

- 70453 Initial map grid line and annotation increments are set correctly for dynamic map extents
- 69527 Map template scale field is editable for dynamic extent in "Fixed Scale" mode

#### Mapping - Wells

<sup>57793</sup> Viewing WES plots and then panning, now re-enables the main menus on the mapping window correctly (Santos Only)

Surface Modeling - Contouring

47182 Replacement connection dialog is displayed when running Contour/Grid (by cell) task

Surface Modeling - Exchange

<u>72771</u> Wells Exchange - Fixed an issue with not being able to set formation system values for selected items

#### Surface Modeling - Gridding

- 72870 Grid/Create Grid from shapefile using formula no longer requests attribute to grid
- 55555 Improved sizing of fault polygons list in gridding
- 73368 Grid input data summary dialog now links to appropriate help topic
- 73136 Grid smoothing now runs when selected after Kriging

Surface Modeling - Volumetrics

72102 Volumetrics thickness reports no longer shows negative thickness

## OpenInventor upgraded to 9.7.2

The OpenInventor toolkit used for rendering content in the 3D Viewer has been upgraded to version 9.7.2. This update provides improved performance and stability, and better support for some graphics cards..

3D Viewer - General

### Visual Studio 2015 OpenMP library now installed 69912

Petrosys PRO now installs the Visual Studio 2015 OpenMP library, which allows 3D Viewer to run on a PC that does not have this library already installed.

## Application - General Enhancements

# During file resolution check any relative files against current project directory 73383

Unresolved data files (e.g. file-based layers in a map) that are stored as relative paths are now prefixed with the current map directory and tested against available path mappings. This helps applications find data files when data files have been moved to a sub-directory, simply add a path mapping from the project directory to the new sub-directory, for example from c:\ PetrosysProjects\MyProject => c:\PetrosysProjects\MyProject\dataFiles.

### Check path mappings against all applicable path mapping

Unresolved data files (e.g. file-based layers in a map) now compare against a wider range of path mappings that may be applicable. For example, on Windows mapped network drives are compared to any UNC paths and paths are compared case-insensitively.

**Application - General** 

## Centreline faults are supported in the Esri ArcMap plugin 73860

The Petrosys PRO plugin for Esri ArcMap now supports drawing of all faults, including centre-line faults.

## Application - User Interface Enhancements

#### Infinite number of decimal places for decimal value entry 71389

Removed the limit of only two decimal places for floating point numbers in the user interface.

Petrosys Release Notes

Petrosys Release PRO 2019.1

Detailed Release Notes

3D Viewer - General

68 entries

#### **Bug Fixes**

73416

## **Bug Fixes**

Enhancements

#### Petrosys Release Notes

#### Removed Dispatch Server and support for Dispatch Server typed connections in the Connection Manager 71518

The Petrosys PRO Dispatch Server daemon is no longer a supported way to connect to remote data sources from Windows. With the introduction of SSH-based connections in PRO 2018.2, this is now the only method of connecting to remote data source. Existing Dispatch Server connections must be migrated over to use this. Please contact Petrosys Support if you require assistance with using remote connections.

#### **Configuration - General** Enhancements

#### Allow From path mapping to be a blank path 73348

Petrosys PRO now allows blank paths to be used for From fields for automated path mapping. This means a path mapping can be added to handle the case where a data file has been moved into a project sub-directory - enter a blank From field with the new location as the To field and automated path mapping will resolve the file location. If the file is then saved, the new path to the data file will be saved.

Path mapping with a blank From field could cause loading of files to be slow, particularly if there are many data files that use path mapping to resolve to their correct location. It is recommended that any blank From field path mappings to be placed at the end of the path mapping list.

Note: if a path mapping with a blank From field has been entered, and then the configuration is saved using an earlier version of Petrosys PRO, then the blank From field path mapping will be removed. This is due to the way earlier versions process paths and can not be changed.

### LIMS - Spotfire links updated (Santos)

using "Edit/License Server Connection Configuration".

Configuration"

Configuration - Licensing Enhancements

## Fixed warning message for Oracle password due to expire

In previous versions, Petrosys PRO would display an empty warning if the Oracle password was due to expire. This has now been fixed and the warning text is now shown.

**Bug Fixes** 

73882

73764

54249

### List filter dialogs now follow parent dialog moves 73075

List filter popup dialog now follow the list dialog when the dialog is moved. In particular, when the list filter is shown, then hidden and then the dialog is moved, and then the list filter is shown again, the filter appears in the expected location. Previously, the list filter would restore the last location it was shown on the screen.

The Spotfire links have been updated at the request of Santos.

#### Petrosys PRO 2019.1 requires a new license file 73012

Petrosys PRO 2019.1 requires a new license file. Petrosys support will make a new license file available for maintained clients. Please contact Petrosys support for any questions on licensing.

Tools/License Manager (Windows) - Leading and trailing spaces are stripped from hostname when using "Edit/License Server Connection

In the Launcher option "Tools/License Manager" on Windows, leading and trailing spaces are stripped from hostname when

Connections, Import and Export Enhancements

## **Application - User Interface**

#### Support added for reading PostGIS spatial data 36485

PostGIS is an extension module for the PostgreSQL database which adds support for GIS and spatial data.

Petrosys PRO now supports reading spatial data from PostGIS spatial databases in a number of contexts:

- Display/GIS
- Spatial Data Translator input
- Grid/Create/Grid input
- Grid/Create/Grid clipping polygons
- Spatial Editor/File/Merge
- Spatial Editor/Clip Polygons
- Mapping/Display/Bubble Maps
- 3D Viewer/Display Point Data
- Volumetrics/Polygons

#### Flash wells option added to Well list for DevKit data sources 72606

Well lists (Mapping/Lists/Wells) for third-party data sources that require a DevKit, such as DUG Insight, Paradigm, Petrel and SeisWare, now have the Display/Flash well option and associated icon, to flash the currently selected well if it has also been displayed on the map. This functionality is the same as already available for SQL based well data sources.

# Drag and drop of 2D seismic horizons now creates a layer with just ribbon map displayed 72525

Drag and drop of 2D seismic horizons from Petrel and DecisionSpace Geosciences into Petrosys PRO Mapping has been changed to create a new 2D seismic line layer with only the ribbon map turned on to show the horizon interpretation. Previously the navigation and line names were also displayed.

#### Petrel Drag-and Drop into grid input data only prompts when required

72520

Drag-and-drop of items from Petrel into the Surface Modeling/Grid/Create grid/Input data list will now only prompt with the add item screen when required.

For example, previously, when a Seismic Horizon is dragged and dropped, the 3D survey or 2D seismic folder and horizon fields were populated appropriately, and it would prompt you to press OK for adding each 3D survey and horizon. Now it simply adds the items to the list, as it has enough information to make a valid input item. On the other hand, if a 3D Seismic survey is dragged and dropped, it will still prompt you to select the horizon to grid.

# Petrel DnD - Dragging 2D Seismic horizons now filters lines by the Petrel survey folder 72278

When a 2D seismic horizon is dragged and dropped into Petrosys PRO Mapping or Surface Modeling, it now creates a layer with the lines filtered by the appropriate 2D seismic survey folder.

#### Connections, Import and Export

#### Performance improved when filtering by Paradigm-Epos well DB 74029

Performance has been significantly improved when filtering Wells by Paradigm-Epos Well\_DBs for Mapping/Display/Wells, Gridding Input data source and Wells exchange. Previously it could take over 1.5 hours to read 2000 wells, where as now it takes about 40 seconds.

# Exchange 3D Seismic Surfaces no longer crashes if it cannot connect to the OpenWorks DevKit 7389

Exchange/3D Seismic Surfaces no longer crashes when OpenWorks is selected as the input data source and it fails to connect to the OpenWorks DevKit.

**Bug Fixes** 

#### Exchange 3D seismic surface more tolerant of geometry differences 73002

In 3D seismic exchange it is now supported for the case that input and output surveys do not match exactly, but the increment of inline/xline of one survey is multiple of the other survey's inline/xline increment and the two survey areas overlap.

#### Connections, Import and Export - Excel Bug Fixes

#### Excel integer values with more than 10 digits are correctly saved 73914

Previously, in contexts where Excel files are written as spatial feature class data (for example Spatial Data Translator, Spatial Editor, Back Interpolate to GIS), Excel numeric values with a large number of digits could be written as blank.

#### Connections, Import and Export - Paradigm-EposEnhancements

#### Added support for Paradigm 18p1 Support Pack on Linux and Windows

73705

70813

The Paradigm 18p1 Support Pack is now supported as a data source in all features that previously supported a Paradigm connection on both Linux and Windows.

Paradigm 15.5, Paradigm 17 and Paradigm 18 continue to be supported as data sources.

#### Connections, Import and Export - Petrel Enhancements

#### Petrel 2019.1 supported

Petrosys connectivity to Schlumberger's Petrel now supports direct interaction with Petrel 2019.1.

Support for Petrel 2019.1 includes the ability to:

- Drag and drop data from Petrel into Petrosys PRO
- > Import Model grid horizons and 3D seismic interpretation horizons to a Petrosys grid file
- > Import faults from Model grids to a Petrosys fault file
- > Import 2D and 3D seismic navigation and horizon interpretation data to a Petrosys SDF
- Directly display Structural framework horizons, Model grid horizons, Input surface grids and 3D seismic interpretation horizons in Mapping
- > Directly contour Structural framework horizons, Model grid horizon data and Input surface grids in Surface Modeling
- > Directly grid 2D and 3D seismic horizon interpretation data in Surface Modeling
- > Directly display, grid and import well data.
- > Directly display 2D seismic navigation and horizon interpretation in Mapping
- Directly display 3D seismic bin grids in Mapping
- > Directly display Structural Model fault surfaces in 3DViewer
- Directly display fault sticks in 3DViewer
- > Export Petrosys and other third party grids to Petrel

Petrosys PRO continues to maintain support for connections to Petrel 2015.x, 2016.x, 2017.x and 2018.x.

#### Petrel 2D seismic - Filtering by Seismic folder is now available in Mapping and Surface Modeling 72635

It is now possible to filter 2D seismic lines from Petrel using a Petrel seismic folder when displaying in Mapping or gridding in Surface Modeling.

#### Petrosys Release Notes

#### Petrel DnD - Default item/layer names are now more descriptive for 2D and 3D horizons

Drag-and-drop of 2D and 3D seismic horizons from Petrel into Petrosys PRO Mapping and Surface Modeling now gives more descriptive and distinct names to each item created, including whether the item is for 2D or 3D seismic, along with the 3D survey name and horizon.

#### Connections, Import and Export - Petrel Bug Fixes

#### Petrel 2D seismic - Import to SDF and dbMap filtering by Seismic folder 72669 now works

The option to filter 2D seismic lines by Petrel folder now works when importing lines from Petrel into SDF (Import/Petrel/Seismic) or dbMap (Mapping/Admin/dbMap Data Transfer/Import/Seismic)

Previously the list of 2D seismic lines would remain empty when this option was used.

dbMap - Client

Mapping - Editors

#### PPDM3.8 Well Checkshot Survey ID, Survey type and Source are now 72973 editable

For dbMap PPDM3.8 clients, the well checkshot survey header dialog now supports editing the Survey ID, Survey type and Source. Previously these fields were read-only.

#### **Documentation - Online Help**

#### Print dialog launches correct help topic

The print dialog has been attached to the relevant help topic.

Mapping - Editors	Enhancements

#### Well Symbol Generator - Added in 72 and 60 degree arc primitives 73977

The /Tools/Well Symbol Generator program has been updated to have 72 and 60 degree arc segment primitives.

#### Spatial Editor reports correct polygon area when projected CRS for data does not have units of metres

Previous versions had an issue where projected coordinates were always assumed to be in metres when reporting lengths and areas for shapes in the spatial editor.

#### Grid Editor requires confirmation when editing contours with ungridded 69379 changes

The grid editor allows a sequence of editing, where a grid can be generated from contours, and then the contours generated from the grid can be selected to be used as the input contours for future edits. The grid editor now requires confirmation prior to updating the input contours if there are changes that have not been gridded.

**Bug Fixes** 

**Bug Fixes** 

73198

**Bug Fixes** 

#### /Display/Text has improved support for international character sets 31024

**Enhancements** 

The /Display/Text option has improved support for international character sets. In most situations any international characters that are entered are preserved and displayed correctly.

#### Improved layer selection in the Display/Web Service Image/WMS layer selector

The layer selector for the Display/Web Map Service/WMS option has been improved to allow layers can be selected from a hierarchy in addition to the existing select and re-order behaviour, which now shows the hierarchical layer name.

#### The selected layer in the Mapping display list is more obviously highlighted 52961

The current layer is shown using a darker colour to make it more obvious that it has been selected.

#### **Display of contours from Petrel added**

Petrel contours can now be displayed in Mapping.

#### Mapping - General

#### Map Templates - Handle Unicode chars correctly when serialised to dbm

72558

**Bug Fixes** 

Map templates now better handle Unicode character sets for items in the legend and other elements. They are correctly saved and loaded via dbm files.

#### Drawing Tools/Closed Shape and Curve - Button double click is more reliable on linux 74051

In the 'Display/Drawing Tools/Closed Shape' and Curve options the double click required to end creation of the line is now more reliable on Linux.

#### Display/Location Map does not crash when enabled for a map with a LocalXY CRS 73557

It is not possible to show a location map for a map using a Local XY CRS as the extent cannot be shown in a wider context. In previous versions, enabling a location map for a map using a Local XY extent would cause a crash.

#### Mapping - GIS, Spatial and Culture Enhancements

#### Display/GIS thematic mapping allows polygon outline lines to be turned off

20227

Display/GIS allows polygon outline to be turned of when setting a thematic polygon fill style. A limitation in previous versions caused the polygon outline to be displayed when just a fill style was desired.

# Display/GIS correctly draws long lines that are close to the central meridian +180 degrees 71420

Petrosys PRO maps are drawn using a projected CRS, to flatten the spherical Earth to a rectangular. Several improvements have been made in Display/GIS to handle certain situations relating to the "wrapping" point of the projected CRS (the central meridian, plus or minus 180 degrees), including correctly handling cases where lines oscillate backwards and forwards across this boundary.

# Display/GIS shows the correct number of decimal places for maps created prior to 2018.3 74002

In Petrosys PRO version 2018.3, the default number of decimal places for numeric attributes in Display/GIS was changed from 6 to 2. This change caused some maps created prior to this version to change to show 2 decimal places instead of 6. The correct number of decimal places will now be shown based on when the map was created.

#### Display/GIS/Thematic Mapping Series Range allows entries of bound between -1.0 and 0.0 72389

Previous versions would incorrectly disallow entry of a value for series range in Display/GIS thematic mapping that was less than 0.0 but greater than -1.0.

#### Mapping - Grids, Surfaces and Sampled Data FilesEnhancements

#### Contour on-the-fly performance improved

Grid colorfill display contour on-the-fly performance is improved about 400% for the case there are many embedded faults or polygon in the Petrosys grid file or many faults are selected for the third-party grid.

### Mapping - Grids, Surfaces and Sampled Data FilesBug Fixes

# Display/Grid contour label size fields are updated correctly when the map scale changes 64318

In previous versions, editing the contours displayed directly from a grid could result in the labels changing relative size.

#### Mapping - Map Sheets

# Initial map grid line and annotation increments are set correctly for dynamic map extents 70453

In previous versions, when Mapping was started with a dynamic extent selected, the map grid lines and border annotation would be set from the data previously displayed, which would more than likely no longer be appropriate.

# Map template scale field is editable for dynamic extent in "Fixed Scale" mode 69527

If the 'Fixed Scale' map template mode is selected, the scale for the map should be able to be explicitly set. In previous versions, this field was incorrectly read-only when a dynamic extent was enabled.

Bug Fixes

#### **Bug Fixes**

Display well path has ability to select multiple path segments for display. This simplifies the display list greatly as only one well layer can be used rather than multiple well layers each with the same well data and different path segment.

## Add support for reading zones from Petrel

Added support for reading zones from Petrel projects.

#### Display/Wells/Path Segments - fixed logic when well intersects formation multiple times 53013

Changed the logic for displaying path well segments.

- > When displaying well path segment from a selected formation to bottom-hole, the deepest measured depth formation is selected (previous versions would use the shallowest measured depth formation) if multiple formations present
- > When displaying well path segment between formations, then the segment is drawn from the shallowest measured depth formation to the other shallowest measured depth formation (previous versions would use the other deepest measured depth formation) if multiple formations present

## Mapping - Wells

#### Viewing WES plots and then panning, now re-enables the main menus on the mapping window correctly (Santos Only) 57793

When viewing WES plots in mapping, then panning around and exiting the WES plot viewer before exiting the panning action the main mapping window will now have its menu activity correctly restored.

## Surface Modeling - Contouring

#### Replacement connection dialog is displayed when running Contour/Grid 47182 (by cell) task

The connection panel pops up when running a contouring task with a third-party connection and the connection has not been established yet.

## Surface Modeling - Exchange

#### Wells Exchanges now supports Log Curve data 43990

The new data type 'Log Curve' has been added to the Wells Exchange framework. As with all other data types, writing Log Curve data can only be done if both the input and output data sources support reading and writing of the data types, respectively.

Wells Exchange supports the reading of Log Curve data from the following data sources:

- > OpenWorks
- Petrel
- IHS Kingdom
- Paradigm
- > ODM
- DUG Insight

display layer



**Enhancements** 

24190

30474

**Bug Fixes** 

**Bug Fixes** 

Enhancements

- Petrosys-dbMap (PPDM38 data model)
- LAS and DLIS files

And has the ability to write to:

- > OpenWorks
- > Petrel
- Petrosys-dbMap (PPDM38 data model)

The use of Log Curves from Petrosys-dbMap with third-party data sources, reads / writes metadata information about the Log Curves in the database, however the sample data is stored in external log files (LAS / DLIS), that are referenced through the Records Management system within the database.

In addition, Wells Exchange has a preview feature of cataloguing LAS and / or DLIS files into a Petrosys-dbMap (PPDM38 data model) database. Information about the files are entered into the Records Management system and files contents metadata is associated to appropriate Wells in the database. This feature will allow data managers to load their Log Curve files and content metadata into dbMap and utilise the power of dbMap/Web to view, and manage the Log Curve metadata through the Web. With the recent introduction of the new Well Log Viewer in dbMap/Web, users will also be able to visualise the Log Curve sample data in the same browser session.

To use this preview feature a user only needs to choose the File based input within Wells Exchange and select their PetrosysdbMap (PPDM38 data model) database as the output data source and like above for third-party data source the 'Log Curve' data type will become available for selection.

#### Exchange/Wells Import Wizard menu has been renamed to Exchange/Wells

46621

For menu naming consistency, the existing Exchange/Wells Import Wizard menu items have been renamed to Exchange/Wells.

### Surface Modeling - Exchange

#### Wells Exchange - Fixed an issue with not being able to set formation system values for selected items 72771

A bug has been fixed that was causing the use of the formation mapping list RMB menu option for setting the output formation group to not allow a user to specify a new name by typing in text to the field rather than selecting an existing system using the + button.

Surface Modeling - General Enhancements

#### Mean and median grid filter added

Mean and Median grid filtering functionality is now available in Surface Modeling through menu item Grid/Processes/Filtering.

#### Lowest closing contour now supports sealing faults that are not closed

Unclosed sealing faults are now supported in LCC.

#### Surface Modeling - Gridding Enhancements

#### Grid outlining performance improved

Grid outlining performance is improved for extremely big grids.

**Bug Fixes** 

15476

73544

#### Boundary gridding displays error message when not valid data

An error message pops up when boundary gridding fails as a result of not having valid data.

# Grid/Create grid allows users to select input point data type (point or line) for GIP, text and Excel data 72382

The gridding of point data from sampled data, text or Excel files offers control over how the input data should be treated for grid estimation process - either as point or line data. The user can set Automatic to have the data processed the same way as in previous versions.

## Surface Modeling - Gridding

# Grid/Create Grid from shapefile using formula no longer requests attribute to grid 72870

Gridding from shapefile and using FORMULA works correctly without setting up the attribute to grid.

#### Improved sizing of fault polygons list in gridding 55555

The fault polygons list is now sized dynamically when the dialog is resized.

#### Grid input data summary dialog now links to appropriate help topic 73368

The input data summary dialog now links to the help topic "Gridding - Create Grid" rather than the "Welcome to Petrosys PRO" page.

#### Grid smoothing now runs when selected after Kriging 73136

The selected smoothing is applied to output grid when Kriging is used.

#### Surface Modeling - Volumetrics Enhancements

#### Use polygons with holes in volumetrics

Volumetrics supports polygons with holes. This will benefit greatly to the lowest closing contour functionality where such polygons are often generated.

#### Surface Modeling - Volumetrics

#### Volumetrics thickness reports no longer shows negative thickness 72102

Volumetrics thickness report does not report negative thickness even though the grid z values are negative for better and more precise volume calculations.

#### Surface Modeling - Workflows/Scripting Enhancements

#### Pause functionality added to Surface Modeling workflows

Added support for pause workflow functionality. This allows the user to perform some operation outside of the workflow (e.g. to edit generated data, or execute some external operation) and then resume the workflow.

73488

**Bug Fixes** 

**Bug Fixes** 

72397

#### Tools/DrawMap scripting now insensitive to template dbm layer order

68862

Surface Modeling Tools/DrawMap tasks no longer rely on the layer order of the template dbm file. I.e. changing the layer order in the template dbm file does not affect the Tools/DrawMap task which still generates the correct result.